
12 Augmenting Path Algorithms

Greedy-algorithm:

- ▶ start with f(e) = 0 everywhere
- find an *s*-*t* path with f(e) < c(e) on every edge
- augment flow along the path
- repeat as long as possible



Augmenting Path Algorithm

Definition 50

An augmenting path with respect to flow f, is a path in the auxiliary graph G_f that contains only edges with non-zero capacity.


Algorithm 45 FordFulkerson(G = (V, E, c))

- 1: Initialize $f(e) \leftarrow 0$ for all edges.
- 2: while \exists augmenting path p in G_f do
- augment as much flow along p as possible. 3:

The Residual Graph

From the graph G = (V, E, c) and the current flow f we construct an auxiliary graph $G_f = (V, E_f, c_f)$ (the residual graph):

- Suppose the original graph has edges $e_1 = (u, v)$, and $e_2 = (v, u)$ between u and v.
- G_f has edge e'_1 with capacity max $\{0, c(e_1) f(e_1) + f(e_2)\}$ and e'_{2} with with capacity max{ $0, c(e_{2}) - f(e_{2}) + f(e_{1})$ }.



Augmenting Path Algorithm

Theorem 51

A flow f is a maximum flow **iff** there are no augmenting paths.

Theorem 52

The value of a maximum flow is equal to the value of a minimum cut.

Proof.

EADS

Let f be a flow. The following are equivalent:

- 1. There exists a cut A, B such that val(f) = cap(A, B).
- 2. Flow f is a maximum flow.
- 3. There is no augmenting path w.r.t. f.

12.1 Generic Augmenting Path

411

Augmenting Path Algorithm

 $\label{eq:1.2} \begin{array}{l} 1. \Longrightarrow 2. \\ \\ \text{This we already showed.} \end{array}$

 $2. \Rightarrow 3.$

If there were an augmenting path, we could improve the flow. Contradiction.

 $3. \Rightarrow 1.$

- Let *f* be a flow with no augmenting paths.
- Let *A* be the set of vertices reachable from *s* in the residual graph along non-zero capacity edges.
- Since there is no augmenting path we have $s \in A$ and $t \notin A$.

12.1 Generic Augmenting Path	
EADS 12.1 Generic Augmenting Path	413

Analysis

Assumption:

All capacities are integers between 1 and C.

Invariant:

Every flow value f(e) and every residual capacity $c_f(e)$ remains integral troughout the algorithm.

Augmenting Path Algorithm

$$\operatorname{val}(f) = \sum_{e \in \operatorname{out}(A)} f(e) - \sum_{e \in \operatorname{into}(A)} f(e)$$
$$= \sum_{e \in \operatorname{out}(A)} c(e)$$
$$= \operatorname{cap}(A, V \setminus A)$$

This finishes the proof.

Here the first equality uses the flow value lemma, and the second exploits the fact that the flow along incoming edges must be 0 as the residual graph does not have edges leaving A.

EADS © Ernst Mayr, Harald Räcke 12.1 Generic Augmenting Path

414

Lemma 53


The algorithm terminates in at most $val(f^*) \le nC$ iterations, where f^* denotes the maximum flow. Each iteration can be implemented in time O(m). This gives a total running time of O(nmC).


Theorem 54

If all capacities are integers, then there exists a maximum flow for which every flow value f(e) is integral.

A bad input


Problem: The running time may not be polynomial.





A bad input

Problem: The running time may not be polynomial.



How to choose augmenting paths?

- We need to find paths efficiently.
- We want to guarantee a small number of iterations.

Several possibilities:

- Choose path with maximum bottleneck capacity.
- Choose path with sufficiently large bottleneck capacity.
- Choose the shortest augmenting path.

EADS © Ernst Mayr, Harald Räcke	12.2 Shortest Augmenting Paths	421

Overview: Shortest Augmenting Paths

These two lemmas give the following theorem:

Theorem 57

The shortest augmenting path algorithm performs at most O(mn) augmentations. This gives a running time of $O(m^2n)$.

Proof.

- ► We can find the shortest augmenting paths in time O(m) via BFS.
- O(m) augmentations for paths of exactly k < n edges.

=[fill=DarkGreen,draw=DarkGreen]

Overview: Shortest Augmenting Paths

Lemma 55

The length of the shortest augmenting path never decreases.

Lemma 56

After at most O(m) augmentations, the length of the shortest augmenting path strictly increases.

EADS © Ernst Mayr, Harald Räcke 12.2 Shortest Augmenting Paths


421

Shortest Augmenting Paths

Define the level $\ell(v)$ of a node as the length of the shortest *s*-*v* path in G_f .

Let L_G denote the subgraph of the residual graph G_f that contains only those edges (u, v) with $\ell(v) = \ell(u) + 1$.

A path P is a shortest s-u path in G_f if it is a an s-u path in L_G .




Shortest Augmenting Path

First Lemma: The length of the shortest augmenting path never decreases.

- After an augmentation the following changes are done in G_f .
- Some edges of the chosen path may be deleted (bottleneck edges).
- Back edges are added to all edges that don't have back edges so far.

These changes cannot decrease the distance between s and t.



Shortest Augmenting Paths

Theorem 58

The shortest augmenting path algorithm performs at most O(mn) augmentations. Each augmentation can be performed in time O(m).

Theorem 59 (without proof)

There exist networks with $m = \Theta(n^2)$ that require $\mathcal{O}(mn)$ augmentations, when we restrict ourselves to only augment along shortest augmenting paths.

Note:

There always exists a set of m augmentations that gives a maximum flow.

EADS © Ernst Mayr, Harald Räcke

12.2 Shortest Augmenting Paths

426


Shortest Augmenting Path

Second Lemma: After at most m augmentations the length of the shortest augmenting path strictly increases.

Let E_L denote the set of edges in graph L_G at the beginning of a round when the distance between s and t is k.

An *s*-*t* path in G_f that does use edges not in E_L has length larger than k, even when considering edges added to G_f during the round.

In each augmentation one edge is deleted from E_L .



Shortest Augmenting Paths

When sticking to shortest augmenting paths we cannot improve (asymptotically) on the number of augmentations.

However, we can improve the running time to $\mathcal{O}(mn^2)$ by improving the running time for finding an augmenting path (currently we assume $\mathcal{O}(m)$ per augmentation for this).

Shortest Augmenting Paths

We maintain a subset E_L of the edges of G_f with the guarantee that a shortest *s*-*t* path using only edges from E_L is a shortest augmenting path.

With each augmentation some edges are deleted from E_L .

When E_L does not contain an *s*-*t* path anymore the distance between *s* and *t* strictly increases.

Note that E_L is not the set of edges of the level graph but a subset of level-graph edges.

EADS © Ernst Mayr, Harald Räcke	12.2 Shortest Augmenting Paths	

Let a phase of the algorithm be defined by the time between two augmentations during which the distance between s and t strictly increases.

Initializing E_L for the phase takes time $\mathcal{O}(m)$.

The total cost for searching for augmenting paths during a phase is at most O(mn), since every search (successful (i.e., reaching t) or unsuccessful) decreases the number of edges in E_L and takes time O(n).

The total cost for performing an augmentation during a phase is only $\mathcal{O}(n)$. For every edge in the augmenting path one has to update the residual graph G_f and has to check whether the edge is still in E_L for the next search.

There are at most n phases. Hence, total cost is $\mathcal{O}(mn^2)$.

428

Suppose that the initial distance between s and t in G_f is k.

 E_L is initialized as the level graph L_G .

Perform a DFS search to find a path from s to t using edges from E_L .

Either you find t after at most n steps, or you end at a node v that does not have any outgoing edges.

You can delete incoming edges of v from E_L .

EADS © Ernst Mayr, Harald Räcke 12.2 Shortest Augmenting Paths

How to choose augmenting paths?

- We need to find paths efficiently.
- We want to guarantee a small number of iterations.

Several possibilities:

EADS

,∐||||∐ (C) Ernst Mayr, Harald Räcke

- Choose path with maximum bottleneck capacity.
- Choose path with sufficiently large bottleneck capacity.

12.3 Capacity Scaling


• Choose the shortest augmenting path.

429

Capacity Scaling

Intuition:

- Choosing a path with the highest bottleneck increases the flow as much as possible in a single step.
- Don't worry about finding the exact bottleneck.
- Maintain scaling parameter Δ .
- $G_f(\Delta)$ is a sub-graph of the residual graph G_f that contains only edges with capacity at least Δ .



Capacity Scaling

Assumption:

All capacities are integers between 1 and C.


Invariant:

All flows and capacities are/remain integral throughout the algorithm.

Correctness:

The algorithm computes a maxflow:

- because of integrality we have $G_f(1) = G_f$
- therefore after the last phase there are no augmenting paths anymore
- this means we have a maximum flow.



Capacity Scaling

Lemma 60

There are $\lceil \log C \rceil$ iterations over Δ . Proof: obvious.

Lemma 61

EADS

EADS

Let f be the flow at the end of a Δ -phase. Then the maximum flow is smaller than $val(f) + 2m\Delta$.

Proof: less obvious, but simple:

- An *s*-*t* cut in $G_f(\Delta)$ gives me an upper bound on the amount of flow that my algorithm can still add to f.
- The edges that currently have capacity at most Δ in G_f form an *s*-*t* cut with capacity at most $2m\Delta$.

434

Capacity Scaling

Lemma 62

There are at most 2m augmentations per scaling-phase.

Proof:

- Let *f* be the flow at the end of the previous phase.
- ► $val(f^*) \le val(f) + 2m\Delta$
- each augmentation increases flow by Δ .

Theorem 63

We need $O(m \log C)$ augmentations. The algorithm can be implemented in time $O(m^2 \log C)$.

EADS © Ernst Mayr, Harald Räcke	12.3 Capacity Scaling	
🛛 💾 🛛 🗋 🕲 Ernst Mayr, Harald Räcke		436

